

## Random DVD menu start (2)

*This how-to describes easy way to start dvd with random menu.*

In previous how-to was used "intro clip" to define string value, which decides about menu start. Now, we define thist string in *VIDEO\_TS.IFO/VMGM\_MAT/First Play PGC* (directly after dvd is started).

For editing is used IfoEdit (<http://www.ifoedit.com>).

Start IfoEdit and open file **VIDEO\_TS.IFO** from our DVD.

Go to **VMGM\_MAT** and **First Play PGC** in the list.

Somwere below is PreCommand (*JumpSS VTSM*) *Jump to TitleSet ...*

This command do jump to menu. There is command *Set GPreg<0> mov (set-val)<1>* before them, which sets jump to menu 1 (sets value 1 for string *GPreg<0>*). We change this command to set random value 1 - 2.

How to edit it?

We change command *GPreg<0>* to value **78 00 00 00 00 02 00 00** in hex editor.

*Note: 78 sets random value, 00 is string number (0) and 02 is count of menus. Values are in hex code (10=A, ..), and can be get from scientist calculator in windows (for example).*

Command was changed to *Set GPreg<0> rnd (set-val)<2>*.

```
set GPreg<1> mov (set-val)<0> [
Set GPreg<0> rnd (set-val)<2> [
(JumpSS VTSM) Jump to TitleSet(vts): 1, Title(ttn): 1, root-menu [
```

Last step is save and test ...